QUADIFIED TEO · PHONE PREPARATION CHECKLIST

Samsung

Mobile ID _____ Test Node _____
Date / by _____

Before Prepare, by hand

- [ ] Enable Developer Options and turn on USB debugging.
- [ ] Turn on Stay awake and Disable adb authorization timeout.
- [ ] Turn off Auto update system.
- [ ] If the phone has a PIN, pattern or password, remove it (Unlock Screen): Prepare cannot remove it.

Connect the phone

- [ ] **Connect the phone** to the Test Node, accept **Allow USB debugging**, and complete its **Mobile ID** on the **Mobile ID's** page: a descriptive name and the real MSISDN, National Format, IMSI and IMEI (Phone Preparation).

Run Prepare

- [ ] **Run Prepare** from the **Mobile ID's** page (Phone Preparation). It applies the steps marked **Done by Prepare** below and emails you the result of each step.

After Prepare, by hand

- [ ] Erase the remaining call forwarding with `##002#` (Disable Call Forwarding Settings).
- [ ] Do any step that the Prepare email lists as failed: each step marked **Done by Prepare** has a **Set it by hand** section for this.

Printable checklists for all brands (PDF)

Full instructions: https://docs.quadified.com/phone-settings/android-settings/samsung/ · Start with the Quick start: https://docs.quadified.com/teo-client-pc-setup/quick-start/

QUADIFIED TEO · PHONE PREPARATION CHECKLIST

Xiaomi

Mobile ID _____ Test Node _____
Date / by _____

Before Prepare, by hand

- [ ] Insert an active SIM card and sign in with a Xiaomi account.
- [ ] Enable Developer Options, then turn on USB debugging, USB debugging (Security settings), Install via USB, Keep screen on, Skip screen lock and Disable adb authorization timeout (step 3).
- [ ] Turn off the screen lock: Prepare does not change it.
- [ ] Turn off Automatic system updates.

Connect the phone

- [ ] **Connect the phone** to the Test Node, accept **Allow USB debugging**, and complete its **Mobile ID** on the **Mobile ID's** page: a descriptive name and the real MSISDN, National Format, IMSI and IMEI (Phone Preparation).

Run Prepare

- [ ] **Run Prepare** from the **Mobile ID's** page (Phone Preparation). It applies the steps marked **Done by Prepare** below and emails you the result of each step.

After Prepare, by hand

- [ ] Erase the remaining call forwarding with `##002#` (Disable Call Forwarding Settings).
- [ ] Do any step that the Prepare email lists as failed: each step marked **Done by Prepare** has a **Set it by hand** section for this.

Printable checklists for all brands (PDF)

Full instructions: https://docs.quadified.com/phone-settings/android-settings/xiaomi/ · Start with the Quick start: https://docs.quadified.com/teo-client-pc-setup/quick-start/

QUADIFIED TEO · PHONE PREPARATION CHECKLIST

Google Pixel

Mobile ID _____ Test Node _____
Date / by _____

Before Prepare, by hand

- [ ] Enable Developer Options and turn on USB debugging.
- [ ] Turn on Stay awake and Disable adb authorization timeout.
- [ ] Turn off Automatic system updates.
- [ ] Set the screen lock to **None**: Prepare does not change it.

Connect the phone

- [ ] **Connect the phone** to the Test Node, accept **Allow USB debugging**, and complete its **Mobile ID** on the **Mobile ID's** page: a descriptive name and the real MSISDN, National Format, IMSI and IMEI (Phone Preparation).

Run Prepare

- [ ] **Run Prepare** from the **Mobile ID's** page (Phone Preparation). It applies the steps marked **Done by Prepare** below and emails you the result of each step.

After Prepare, by hand

- [ ] Erase the remaining call forwarding with `##002#` (Disable Call Forwarding Settings).
- [ ] Do any step that the Prepare email lists as failed: each step marked **Done by Prepare** has a **Set it by hand** section for this.

Printable checklists for all brands (PDF)

Full instructions: https://docs.quadified.com/phone-settings/android-settings/pixel/ · Start with the Quick start: https://docs.quadified.com/teo-client-pc-setup/quick-start/

QUADIFIED TEO · PHONE PREPARATION CHECKLIST

iPhone

Mobile ID _____ Test Node _____
Date / by _____

- [ ] Connect the iPhone to the Mac and tap **Trust** (Before you start).
- [ ] Turn on Developer Mode and check it.
- [ ] Wi-Fi on, Airplane Mode off.
- [ ] Portrait Orientation Lock on.
- [ ] Auto-Lock **Never**, **Raise to Wake** on, Low Power Mode off.
- [ ] Passcode off.
- [ ] Ringer volume at the minimum, **Change with Buttons** off.
- [ ] 24-Hour Time on and the time set automatically.
- [ ] Messages: Default Messaging App is Messages, MMS Messaging and Group Messaging on, RCS Messaging and iMessage off; on iOS 26 and later, Screen Unknown Senders off.
- [ ] Erase all call forwarding with `##002#`.
- [ ] iOS 26 and later: Screen Unknown Callers set to **Never**.
- [ ] Complete the Mobile ID on the **Mobile ID's** page: name, MSISDN, National Format, IMSI and IMEI (see Edit a Mobile ID).

Printable checklists for all brands (PDF)

Full instructions: https://docs.quadified.com/phone-settings/ios-settings/ · Start with the Quick start: https://docs.quadified.com/teo-client-pc-setup/quick-start/